



16.0 Height and Crown Diameter Assessments

Contents

16.0 Height and Crown Diameter Assessments	2
16.1 Assigning Sample Height Trees	2
16.2 Sample Height tree types:	3
16.3 Total Height	4
16.4 Height Measurement Conventions.....	5
16.4.1 Distance from the Tree	5
16.4.2 Assessing Tree Heights on a Slope	6
16.4.3 Assessing Leaning Trees	6
16.5 Crown heights and diameter	7
16.5.1 Crown Heights	7
16.5.1.1 Upper Crown Height:	7
16.5.1.2 Lower Crown Height:	7
16.5.2 Crown Diameter	8

Figures

Figure 16 - 1: Total height points on conifers (a) and broadleaves (b).	4
Figure 16 - 2: Distance from the tree.....	5
Figure 16 - 3: Measuring tree height on sloping ground.....	6
Figure 16 - 4: Measuring tree height on leaning trees.....	6
Figure 16 - 5: Upper and Lower Crown Height	7
Figure 16 - 6: Crown diameter - plan view.....	8
Figure 16 - 7: Crown diameter – side view	8

NFI Survey Manual Section 16: Height and Crown Diameter Assessments


16.0 Height and Crown Diameter Assessments

(Height assessment methodologies from Matthews & Mackie (2006) Forest Mensuration, A handbook for Practitioners, FC, Edinburgh).


16.1 Assigning Sample Height Trees

The software will assign all the sample height trees (except the Dominant Height tree per storey which has to be assigned manually) as long as there are enough trees within the plot. Where necessary trees outwith the plot may need to be assigned manually using the Tree Type field.

For Whole Section plots



For circular plots



NFI Survey Manual Section 16: Height and Crown Diameter Assessments

16.2 Sample Height tree types:

- Dominant Height tree (Circular plots only)
 - This is the largest diameter tree within *each* Storey in the plot.
- 1st Stand Height Tree (Whole Section points only)
 - This tree is selected by the Allocate Sample Trees function in the software – see **Chapter 14.0**.
- 2nd Sample Tree (for Circular and Whole Section Plots)
 - This is usually assigned using the Auto-Assign Sample Trees (circular plots) or Allocate Sample Trees (whole Section plots) options in the software. If assigned manually it should be the 3rd nearest Neighbour to the 1st Stand Height or Dominant Height tree within the same storey. Note that for counting between trees only live trees are to be counted. Also coppice stools/multi-stem trees are counted as a single entity (e.g. count the stool) and not counted for each individual stem. The tree must be within the *Section* boundary but, for circular plots, can be outside the Square where the Section extends outside the Square.
- 3rd Sample Tree (for Circular and Whole Section Plots)
 - This is usually assigned using the Auto-Assign Sample Trees (circular plots) or Allocate Sample Trees (whole Section plots) options in the software. If assigned manually it is the 3rd nearest tree to the 2nd Sample Tree within the same storey. Note that for counting between trees only live trees are to be counted. Also coppice stools/multi-stem trees are counted as a single entity (e.g. count the stool) and not counted for each individual stem. The tree must be within the *Section* boundary but, for circular plots, can be outside the Square where the Section extends outside the Square.

Mapping the location of the Dominant, 1st Stand Height and 2nd & 3rd Sample trees is important to allow the QA staff to relocate them.

NB: Live trees - only unsnapped trees which are not excessively leaning ($\geq 20^\circ$) can be assessed for height.

Dead Trees – estimate individual tree heights within the plots, these can be snapped and only the actual height is estimated (tops are not added back on for snapped trees).

NFI Survey Manual Section 16: Height and Crown Diameter Assessments

16.3 Total Height

For the National Forest Inventory (NFI) the Total height of the trees is required. Total height is the *vertical* distance from the base of the tree to the uppermost point (tip) for live trees.




Figure 16 - 1: Total height points on conifers (a) and broadleaves (b).

During the NFI all tree heights are to be assessed either directly with tapes or indirectly using a Vertex hypsometer.

When assessing windblown trees the stem length is assessed to give an indication of total height as if the tree was standing.

NFI Survey Manual Section 16: Height and Crown Diameter Assessments

16.4 Height Measurement Conventions

16.4.1 Distance from the Tree

The distance between the observation point and the tree ('d' in Figure opposite) should be in the region of 1 to 1.5 times the height of the tree.

Errors can prove to be sizeable where the observer is closer than this. The main difficulty in achieving the ideal position is being able to view the tops of trees in dense stands.

The height of the tree is always the *vertical* distance between the top and the base. The precision of the measurement is inevitably related to the capability of the instrument used.





Figure 16 - 2: Distance from the tree

Take care to find the true total height point and do not sight on a side branch. This can be especially difficult when measuring broadleaved trees.



NFI Survey Manual Section 16: Height and Crown Diameter Assessments

16.4.2 Assessing Tree Heights on a Slope

On sloping ground it is necessary to correct the measured distance to the tree to obtain this (Figure 16-3). The Vertex hypsometer will do this automatically if used correctly.




Figure 16 - 3: Measuring tree height on sloping ground.

16.4.3 Assessing Leaning Trees

Trees should be checked for lean and direction of lean. If the tree is leaning the measurement should be taken at right angles to the direction of lean (see opposite). Height should be measured as the vertical distance from the tip of the tree to the ground. Strictly the distance from the observer to the tree should also be measured from a point on the ground vertically below the tip. However, it may be expedient to measure this distance from the base of the tree.

Trees with excessive lean ($\geq 20^\circ$) are unsuitable for the assessment of height unless the entire Storey is leaning excessively.




Figure 16 - 4: Measuring tree height on leaning trees.

NFI Survey Manual Section 16: Height and Crown Diameter Assessments

16.5 Crown heights and diameter

16.5.1 Crown Heights

16.5.1.1 Upper Crown Height:

Conifers: The height on the main stem (insertion point) where the **lowest complete live whorl** of branches occurs, recorded to the nearest 0.1 m.

Broadleaves: The height on the main stem where the **lowest complete live circle** of foliage occurs, recorded to the nearest 0.1 m.

16.5.1.2 Lower Crown Height:

Conifers: The height of **the lowest live branch** (excluding epicormics and forks) insertion point that is connected to the crown, recorded to the nearest 0.1 m.

Broadleaves: The height of **the lowest level of foliage** that is connected to the crown (excluding epicormics and forks), recorded to the nearest 0.1 m.




Figure 16 - 5: Upper and Lower Crown Height

NFI Survey Manual Section 16: Height and Crown Diameter Assessments

16.5.2 Crown Diameter

The diameter of the crown should be measured along a North – South bearing first and then along an East – West bearing, from drip line to drip line. Measure to the actual drip line along these axes and do not tree to take the average of the crown at that point.

PLAN VIEW




Figure 16 - 6: Crown diameter - plan view

Measure across the visual centre of the crown (tip: put the vertex pole under the crown centre) rather than across the base of the stem. In some cases the crown does not sit above the stem base.




Figure 16 - 7: Crown diameter – side view